# **User Manual**

Version 1.0

# **Project:**

TB Portal UPM

# **1.0 Overall Project Structure**

System URL : https://tbgisgombak.com/arcgis/




Figure 1.1 Overall System Structure

# 1.1 Pre-Login

GIS APPLICATION	INTRODUCTION	DOWNLOAD	CONTACT	
				-

#### Figure 1.2 Pre-Login Function Tabs

4 Tab(s) are available upon access into system URL which can be found on top left corner as in Figure 1.2 consists of :

- 1. GIS Application
- 2. Introduction
- 3. Download
- 4. Contact

#### 1.1.0 GIS Application



Figure 1.1.0 GIS Application Tab

In GIS Application tab, user are allow to login to Portal TB via username and password accordingly.

# 1.1.1 Introduction



Figure 1.1.1 Introduction

Introduction page consists of introduction content retrieved from PDF stored in server. To update the content, kindly refer to section 3.0.

# 1.1.2 Download



Figure 1.1.2 Download

Download tab consists of downloadable file which are :

- 1. System flow chart
- 2. Publication document
- 3. User Manual

To update the content, kindly refer to section 3.0.

# 1.1.3 Contact



Figure 1.1.3 Contact

Contact tab consists of contact information of person-in-charge of this project.

To update the content, kindly refer to section 3.0.

# 2.0 Post-Login

#### 2.1 Map List

Home v	Map List							
Upload Map	Show 25 v er						Search:	
	Map ID	Il Map		11 View	Export Data	Remove	Created Time	
	2	TB 20	113 - 2017	Data Map	Download	Remove	2020-12-01 09:22:35	
	Showing 1 to 1 of 1 er	ntries						Previous Next

Figure 2.1.0 Map List Page

1t	View 11	Export Data	Remove 11
	Data Map	Download	Remove

Figure 2.1.1 Map Data Column

In Map List page, user are able to :

- 1. View GIS data uploaded by click on "Data" button in view column as illustrated in Figure 2.1.1.
- 2. View GIS Map in map view by click on "Map" button in view column as illustrated in Figure 2.1.1.
- 3. To Export data uploaded, click on "Download" button in export data column as illustrated in Figure 2.1.1
- 4. To remove data uploaded, click on "Remove" button in remove column, do note that this operation is not reversible.

#### 2.2 Upload Map Data



Figure 2.2.0 Side Navigation Bar

To upload map data, click "Upload Map" on the side navigation bar as in Figure 2.2.0.

Portal TB Gombak	=		
	-		
Beneral.			
Map List	Add Map Data		
<ul> <li>Upload Map</li> </ul>			Reset
	Ma	Name * 29/10/2020	
	Pi Contra	Jpload* Choose File No file chosen	
			Submit
			Scoret

Figure 2.2.1 Upload Map Data Page

To upload new map data, click on "Choose File" button and select desire CSV file, fill in "Map Name" as an identifier and hit "Submit" on the bottom right corner. A "Upload Success" message will be observe once the upload process is successful.

### 3.0 Replace Pre-Login Content

Step 1 : Login into hostinger cPanel

HOSTINGER
Log In
fOG
Log in with Facebook Email Address
Password
Log in
Forgot password?
Not a member yet? Welcome on board - Sign up now!

Figure 3.0 Hostinger Login Page

Step 2 : Choose "File Manager" in the list




Figure 3.1 File Manager Function In cPanel

Step 3 : Select "public\_html" folder



Step 4 : Access to arcgis/assets/

Name <b>T</b>	Size
💼 css	
adownloadable	
aud_select	
🖬 images	
🖬 img	
🖬 js	
test_asset	
Contact.pdf	44.9 kB
intro.pdf	65.3 kB

Figure 3.3 Project Path

To replace "Contact" and "Introduction", kindly upload (drag file) into the browser to replace "contact.pdf" and "intro.pdf" with **EXACT same file name and its extension**.

Name <b>V</b>	Size
download_flow.jpeg	39.8 kB
download_tb2.pdf	484.5 kB
download_user.pdf	484.5 kB

#### Figure 3.4 Downloadable Folder

"downloadable" folder as in Figure 3.3 contains file to download in "Download" tab as in section 1.1.2. To replace, kindly upload (drag file) into the browser and replace the file with **EXACT same file name and its extension**.